

Lakota Network Setup Instructions
Windows XP
Technical Support 1-888-256-8372

UserID _____

Password _____

Basic Dial-Up Setup Information

1. From the desktop, click the **Start** button. Go to **All Programs, Accessories, Communications**, then **New Connection Wizard**.
2. A dialog box Welcome to the New Connection Wizard will open. Click **Next**.
3. Select **Connect to the Internet**. Click **Next**.
4. Select **Setup my connection manually**. Click **Next**.
5. Select **Connect using a dial-up modem**. Click **Next**.
6. In the field For ISP Name, enter **Lakota Network**. Click **Next**.
7. In the field for Phone number, enter 964-9999 or 865-3483 (for Timberlake customers), click **Next**.
8. For Enter Internet Account Information, enter your **User ID** for Username, **Password**, and enter your password again to Confirm Password. Click **Finish**.
9. From the desktop, click on the **Start** button. Go to **All Programs**, then **Accessories, Communications**, and then **Network Connections**.
10. Alternate click (right click) on the **Lakota Network** icon, from the menu, select **Properties**.
11. Select the **Networking** tab and ensure **PPP: Windows 95/98/NT 4/2000, Internet** is selected.
12. Click on **Internet Protocol (TCP/IP)** to highlight it and select **Properties**.
13. Ensure **Obtain DNS server address automatically** radio button is selected.
14. Then click **OK** until all dialog boxes are closed.

Basic E-mail Setup Information

1. From the desktop, click on the **Startup** and select **E-mail - Outlook Express** from the menu. This will open your e-mail application.
2. From the main menu select **Tools**. From the drop menu, select **Accounts...** (this will launch a window with four tabs to choose from).
3. Select the **Mail** tab and click **Add** then select **Mail**. This will open a wizard with the following:
 - a. For **Display name**: enter your name:
example (John Doe). Click **Next**.
 - b. For **E-mail address**: enter your e-mail address in the following format:
example (userid@lakotanetwork.com). Click **Next**.
 - c. Ensure **POP3** for the incoming mail server is selected and enter the following:
Incoming Mail Server: **pop.lakotanetwork.com**
Outgoing Mail Server: **mail.lakotanetwork.com** Then, click **Next**.
 - d. For **Account name**: enter your **User ID** and then your **Password**. Click **Next** and **Finish**.
 - e. Double-click on **pop.lakotanetwork.com** and choose a name of your choice for your account.
example: (John Doe's Mail). Click **Apply** then **Ok**.

**If you have any trouble setting up your connection, you may call the
Technical Support toll free number listed above.**